

Microlab® 600 Qualification Procedure

March 2023

Table of Contents

Introduction	3
Section 1: Installation Qualification	3
Section 2: Operational Qualification	4
Section 3: Performance Qualification	F



Introduction

This procedure defines the general steps that should be performed to ensure that the Microlab 600 is installed and functioning correctly. This document references sections from the Microlab 600 Basic Manual (P/N 61440-01).

Section 1: Installation Qualification

1.1	Select the proper location for the Microlab 600 (Section COMPLETE	,
1.2	Unpack the Microlab 600.	Serial Number
COMPLETE		Pump
1.3	Record the pump and controller serial numbers here:	Controller
1.4	Connect the power supply with the power cord to the GOMPLETE	e pump.
	The valve(s) will already be installed on the Microlab 600. For ng new valves, reference Section 2.4.1.	questions on removing or
1.5	Install the fill and dispense tubing assemblies (Section COMPLETE	1 2.4.3).
1.6	Install the Accessory Holder and Tubing Managemen (Section 2.4.4 – 2.4.5).	t System
1.7	Record the hand probe or foot switch to be used here (e.g. Concorde CT, Dual Push Button, or other)	Probe/Switch
1.8	Install the hand probe or foot switch (Section 2.4.6). ☐ COMPLETE	
1.9	Install the controller (Section 2.5).	
	COMPLETE	Syringe Volumes
1.10	Turn the instrument on. □ COMPLETE	Left
1.11	Record the syringe volumes to be used here:	Right
	using a single syringe dispenser, there will only be one syring	re (left)
1.12	Prepare the syringe(s) for use (Section 2.4.2).	yo (iori).
1.12	☐ COMPLETE	
1.13	Install the syringe(s) on the instrument (Section 2.4.2). \Box COMPLETE	
Print N	lame:	
Signat	ure:	Date:



Section 2: Operational Qualification

2.2 Configure the instrument				
2.2 Configure the instrument.				
2.2.1 In the Hardware Configuration screen, select the Syringe and select the size of syringe(s) (Section 4.2.1). □ COMPLETE				
2.2.2 In the Hardware Configuration screen, select the Valve and select the type of valve configuration (Section 4.2.2). ☐ COMPLETE				
2.3 Prime the instrument with deionized water (Section 4.4). □ COMPLETE				
2.4 Create a new method. □ COMPLETE				
2.4.1 For Basic controlled instruments, select the volume to the capacity syringe(s) (Section 4.5).	city of the			
2.4.2 For Advanced controlled instruments, select the Quick Start but and run the method using the Basic Run Screen (Section 4.5).				
2.4.2.1 For Advanced Dual Syringe Dispensers, set the left and r the capacity of the syringes. Perform a dispense, testing of the instrument.				
of the syringe and the right side to zero to verify the left	For Advanced Dual Syringe Diluters, set the left side to the capacity of the syringe and the right side to zero to verify the left syringe. Then repeat this step with the left side set to zero with the right side at the syringe capacity.			
2.4.2.3 For Dual Syringe Continuous Dispensers, set the volum syringes to capacity as one syringe fills the other disper Triggering the pump will test the left side and then trigger the pump again will test the right side.	nses.			
2.4.3 Record Firmware FPGA, Firmware Runtime Version, Software Version, and Operating System Version here: Firmware				
2.5 Run the new method (Section 4.5). FPGA □ COMPLETE FPGA Firmware Runtime				
2.6 Dispense the deionized water on an analytical software balance to determine whether the instrument	Э			
is dispensing as expected. □ COMPLETE Operating System	ng			
Note: The diluter configuration will aspirate from the right syringe. The probe mussubmerged into the reservoir when the aspiration step is triggered. For a dilution total volume dispensed will be equal to the left diluent volume plus the right sample.	method, the			
Print Name:				
Signature: Date:				



Section 3: Performance Qualification

3.1 Getting Started.

This is a general qualification procedure for methods run on the Microlab 600. The technique is based on weighing deionized water samples delivered by the instrument. The true volume is then calculated based on the density of water at the sampling temperature.

Note: This method is not recommended for volumes below 2 µL. There is no upper volume limit.

- 3.1.1 Create a method to be validated (Section 4.5).
 ☐ COMPLETE
- 3.1.2 Identify critical dispenses where gravimetric verification is required.

 □ COMPLETE
- 3.1.3 Identify acceptable accuracy and precision criteria for the critical dispenses.

 ☐ COMPLETE
- 3.1.4 Test the Microlab 600 by running the method and verify dispense accuracy and precision (Section 4.5).

 □ COMPLETE
- 3.2 Equipment, Materials, and Environment.

□ COMPLETE

3.2.1 Laboratory balances required for the test method should meet or exceed the following performance specifications. They must be regularly maintained and calibrated with the appropriate N.I.S.T. traceable weights.

Reference Table 3-1 for details.

Table 3-1: Required Balance Sensitivity for Dispense Volumes

Test Volume, µL	Balance Sensitivity, mg
1 – 10 μL	0.001 mg
10 – 100 μL	0.01 mg
100 – 1,000 μL	0.1 mg

- 3.2.2 Use a balance table or suitable equivalent to minimize vibration. Cover the working surface directly in front of the balance with a dark, smooth, non-glare material. Keep the balance area reasonably free of draft currents and the ambient area free of excessive dust.
- 3.2.3 Use a weighing vessel that has a total volume 12 to 40 times the test volume, or $500~\mu L$, whichever is larger (this is for evaporation control). If possible, use a cover that fits over the outside of the vessel top (do NOT allow the cover to come into contact with the test liquid). The vessel should be plastic, glass, metal, or some other non-porous material. The cross-sectional area of the opening should be as small as possible to further control evaporation.



- 3.2.4 Handle the vessel with forceps or tweezers.
- 3.2.5 Use deionized water that has equilibrated to room temperature.
- 3.2.6 Use a calibrated thermometer to measure the temperature of the water.
- 3.3 Test Procedure.
 - 3.3.1 Turn on all equipment and allow all test materials to equilibrate to room temperature.
 - 3.3.2 Place a small amount of water in the weighing vessel (between 2 and 30 test volumes).
 - 3.3.3 Prime the Microlab 600 to eliminate all air bubbles from the fluid path.
 - 3.3.4 Run the method to be validated.
 - 3.3.5 Open the door of the balance chamber, place the weighing vessel on the balance pan, and close the door of the balance chamber.
 - 3.3.6 Tare the balance. Retrieve the weighing vessel from the balance chamber, deliver the sample, and return the vessel to the balance pan, closing the door to the chamber. Observe and record balance readout.
 - 3.3.7 Deliver a total of *n* samples (*n*=10 is recommended) into the weighing vessel, and weigh each sample after delivery. Replicate all motions and time intervals in each sampling cycle as precisely as possible. Keep the distance between the balance and the diluter/dispenser to a minimum. Use Table 3-2 to record the dispense masses.
 - 3.3.8 Measure and record the water temperature below:

Test Volume 1 Temperature: Start		Average
		- 3 -
Test Volume 2 Temperature: Start	Finish	Average
Test Volume 3 Temperature: Start	Finish	Average

 Table 3-2: Recorded Masses of Each Dispense

		•	
Dispense Replicate	Test Volume 1 (grams)	Test Volume 2 (grams)	Test Volume 3 (grams)
1			
2			
3			
4			
5			
6			
7			
8			
9			
10			



3.4 Calculations.

3.4.1 Calculate the volume of each dispense (V_i) by dividing each mass value by the density of water at the measured temperature. Refer to Table 3-3 below for density values. Use Table 3-4 to record the calculated values.

Table 3-3: Density of Water at Various Temperatures

°C	g/mL	°C	g/mL
17	0.998774	24	0.997296
18	0.998595	25	0.997044
19	0.998405	26	0.996783
20	0.998203	27	0.996512
21	0.997992	28	0.996232
22	0.997770	29	0.995944
23	0.997538	30	0.995646

Taken from CRC Handbook of Chemistry and Physics, 50th Edition, 1969, page F – 4.

Table 3-4: Calculated Dispense Volume

Dispense Replicate Vi Value	Test Volume 1 (mL)	Test Volume 2 (mL)	Test Volume 3 (mL)
V ₁			
V_2			
V_3			
V_4			
V_5			
V_6			
V_7			
V_8			
V_9			
V ₁₀			

3.4.2 Calculate the average dispensed volume from the individu	
volumes, V_i (where "i" is 1 to 10): $V_{avg} = (V_1 + V_2 + V_3 + Use the data collected in Table 3-4 to calculate the V_i and$	+ V ₁₀) / 10.
Use the data collected in Table 3-4 to calculate the V_i and	record below:

Average Dispense Volume (Vava) for Test Volume 1:
Average Dispense Volume (V _{avg}) for Test Volume 2:
Average Dispense Volume (V _{avg}) for Test Volume 3:
- avy



3.4.3 Calculate the syringe accuracy: Accuracy (%) = 100 x ($V_{avg} - V_{o}$) / V_{o} . Use Table 3-5 to record the data.

Note: V_0 is equal to the expected dispense volume.

3.4.4 Calculate the standard deviation of the calculated volumes: (STDEV) = $\sqrt{\frac{(V_1 - V_{avg})^2 + (V_2 - V_{avg})^2 + (V_3 - V_{avg})^2 + (V_3$

Table 3-5: Accuracy and Precision

Table 6 617 to 681 do 9 di 14 1 1 6 6161 di			
	Test Volume 1	Test Volume 2	Test Volume 3
Calculated Accuracy			
Allowable Accuracy			
Calculated Precision			
Allowable Precision			
Test Results (Pass/Fail)			

Observations:	
Print Name:	
Signature:	Date:

© 2023 Hamilton Company. All rights reserved. All trademarks are owned and/or registered by Hamilton Company in the U.S. and/or other countries. Lit. No. L10064 Rev. F - 03/2023



 Hamilton Americas & Pacific Rim

Hamilton Company Inc. 4970 Energy Way Reno, Nevada 89502 USA Tel: +1-775-858-3000 Fax: +1-775-856-7259 sales@hamiltoncompany.com Hamilton Europe, Asia & Africa Hamilton Central Europe S.R.L. str. Hamilton no. 2-4 307210 Giarmata, Romania Tel: +40-356-635-050 contact.lab.ro@hamilton.ch

8